
Subject: How to set the location of the swap file XP
Posted by [brandon\[2\]](#) on Wed, 21 Feb 2007 03:06:00 GMT
[View Forum Message](#) <> [Reply to Message](#)

I set the swap file on its own drive before. Now I want to set it back where it goes normally. How do I do that?
thx
b

Subject: Re: How to set the location of the swap file XP
Posted by [xpam_mark](#) on Wed, 21 Feb 2007 07:19:59 GMT
[View Forum Message](#) <> [Reply to Message](#)

Put it back on C:/

W Mark

"brandon" <a@a.com> wrote in message news:45dba908\$1@linux...
>
> I set the swap file on its own drive before. Now I want to set it back
> where
> it goes normally. How do I do that?
> thx
> b

Subject: Re: How to set the location of the swap file XP
Posted by [Chris Ludwig](#) on Wed, 21 Feb 2007 16:48:50 GMT
[View Forum Message](#) <> [Reply to Message](#)

Hi Brandon,

Right click on "My Computer" go to properties/advanced/performance settings/advanced/virtual memory. press the change button
First select the C drive then select custom size set the min max to the same amount. For 1 gig of ram use 3072 as min./max, for 2 gigs use 4096.
Second select each of the other drives listed and choose 'No paging File' for each drive other than the C drive.
Press OK then apply and then reboot and you should be good.

Chris

Brandon wrote:
> I set the swap file on its own drive before. Now I want to set it back where

> it goes normally. How do I do that?
> thx
> b

--

Chris Ludwig

ADK Pro Audio
(859) 635-5762
www.adkproaudio.com
chrisl@adkproaudio.com

Subject: Re: How to set the location of the swap file XP
Posted by [Mark McDermott](#) on Wed, 21 Feb 2007 18:26:58 GMT
[View Forum Message](#) <> [Reply to Message](#)

Click Start, then right-click My Computer and select Properties.

Click the Advanced tab, then click the Settings button in the Performance pane.

Click the Advanced tab, then click Change in the Virtual Memory pane.

You can set your swap file location/size here.

Pretty simple, eh?

Thanks Bill G for the wonderful UI!

Mark

"brandon" <a@a.com> wrote:

>
>I set the swap file on its own drive before. Now I want to set it back where
>it goes normally. How do I do that?
>thx
>b
